

10th NUCLEONICA Training Course, Çesme, Turkey, 8-10th Oct. 2008


NUCLEONICA: Mass Activity Calculator

J. MAGILL


*European Commission, Joint Research Centre,
Institute for Transuranium Elements,
Postfach 2340, 76125 Karlsruhe, Germany*



Nuclear science applications...

 ... web driven nuclear science

ApplicationsMy PreferencesHelp

> Nuclide Explorer

» Actual Chart: Karlsruhe
> Search Nucleonica Documentation

Nuclear Data Retrieval

> Application Centre

- » **Mass Activity Calculator**
- » Decay Engine
- » Dosimetry & Shielding
- » Range & Stopping Power
- » webKORIGEN
- » Universal Nuclide Chart
- » Transport & Packaging
- » Nuclide mixtures
- » Nucleonica Scripting
- » Library creation for 3rd party software
- » Radiological Dispersion Module
- » Extended Graph Module

> Data Centre

- » Physical Constants
- » Nuclide Datasheets
- » Nuclide Derived Data
- » Average Cross Sections
- » Radiations
- » Prompt Gamma
- » Fission Yields

> Knowledge Centre

- » Nuclear News
- » Reading room
- » Useful Weblinks
- » Ask An Expert
- » Element Information
- » Conference Calendar

Welcome, Joe
Edit PreferencesAdministration
MyCommunity Portal

> My Last Nuclides

- » 90 Th232
- » 90 Th231
- » 94 Pu239
- » 92 U235
- » 25 Mn52

> My Nuclide Mixtures

- » Pu238+daughter (100g @50y)
- » Natural Uranium
- » Cs137 + Ba137m
- » U232+Co60
- » Transuranics in 1 ton Spent Fuel (4.2% enriched, 50GWd/t, 6 years cooling)

> My Sources

- » Pu239 1 g
- » natu


> My Messages

- » Thanks!
- » About my group and information
- » Photo Change
- » Open call for JRC Traineeships at the Institute for Transuranium Elements
- » NAML-9 International Conference on Nuclear Analytical Methods in the Life Sciences

> User Alerts


- » Task completed (DecayEngine: Uranium 238)

Example of a simple NUCLEONICA application: The Mass-Activity Calculator



... web driven nuclear science

[Applications](#) [My Preferences](#) [Print](#) [Help](#)




Mass Activity Calculator

27 Cobalt

Actual Chart: Karlsruhe


Element: Mass:



Unit: Quantity

Unit	Quantity
Grams	1.0000E+00
Becquerel	4.1871E+13
Curies	1.1317E+03
Number of Atoms	1.0048E+22

Version 1.0.0000.0096



Help: Mass Activity Calculator


[help](#) [discussion](#) [edit](#) [history](#) [delete](#) [move](#) [watch](#)

Contents [hide]

- 1 Introduction
- 2 Nuclide Selector
- 3 Unit/Quantity Selector
- 4 Unit Conversion
- 5 Simple Decay and the Decay Constant

Introduction

The mass activity calculator is used to convert between the number of atoms, activity (Bq or Ci) and mass (g) for a specific nuclide.




Mass Activity Calculator

27 Cobalt

Actual Chart: Karlsruhe

Element: Mass:



Unit: Quantity

Unit	Quantity
Grams	1.0000E+00
Becquerel	4.1871E+13
Curies	1.1317E+03
Number of Atoms	1.0048E+22

Mass Activity Calculator interface showing the Nuclide Selector, Unit/Quantity selector, and the Unit/Quantity Table.

navigation

- [Main Page](#)
- [Community portal](#)
- [Current events](#)
- [Recent changes](#)
- [Random page](#)
- [Help](#)
- [Glossary](#)

search

toolbox

- [What links here](#)
- [Related changes](#)
- [Upload file](#)
- [Special pages](#)
- [Printable version](#)
- [Permanent link](#)

Example of a simple NUCLEONICA application:

The Mass-Activity Calculator:

Unit Conversion [\[edit\]](#)

The conversion from mass to number of atoms N , and vice versa, is obtained using

$$N = \text{Mass}(g) \cdot N_A / M$$

where N_A is Avogadro's number, M is the atomic mass of the nuclide. The conversion from number of atoms to activity, and vice versa, is obtained using

$$\text{Activity}(Bq) = k \cdot N = \ln 2 \cdot N / \tau$$

$$\text{Activity}(Ci) = \text{Activity}(Bq) / 3.7 \cdot 10^{10}$$

where k , and τ are the decay constant and half-life respectively of the nuclide. It follows that the relation between activity and mass is given by

$$\text{Activity}(Bq) = (\ln 2 / \tau) \cdot \text{Mass}(g) \cdot N_A / M$$

Simple Decay and the Decay Constant [\[edit\]](#)

For [simple radioactive decay](#) processes in which a parent nuclide decays and there is no source term for the production of the parent, the equation for radioactive decay is given by:

$$dN/dt = -kN$$

where N is the number of atoms at time t and k is the decay constant. The [Activity](#) is the number of disintegrations per unit time i.e. $\text{Activity} = -dN/dt = kN$. The decay constant is related to the [half-life](#) τ through the relation

$$k = \ln 2 / \tau \approx 0.693 / \tau$$

It follows that the number of atoms as a function of time is given by

$$N(t) = N(0) \cdot e^{-kt} \text{ or alternatively } N = N(0) \cdot \left(\frac{1}{2}\right)^{t/\tau}$$


and the activity as a function of time is given by

$$\text{Activity}(t) = \text{Activity}(0) \cdot e^{-kt} \text{ or alternatively}$$


$$\text{Activity}(t) = \text{Activity}(0) \cdot \left(\frac{1}{2}\right)^{t/\tau}$$

The expressions involving the term $\left(\frac{1}{2}\right)^{t/\tau}$ are useful for calculating directly with the decay time t and the half-life τ .

Example of simple NUCLEONICA application:

... web driven nuc

Applications My Preferences Print Help



Mass Activity Calculator
27 Cobalt

Actual Chart: Karlsruhe

Element: Mass:
Co 60

Unit Quantity

Grams 1

Update

Unit	Quantity
Grams	1.0000E+00
Becquerel	4.1871E+13
Curies	1.1317E+03
Number of Atoms	1.0048E+22

Version 1.0.0000.0096

Nuclide Selector

[\[edit\]](#)

In the Mass Activity Calculator, the nuclide Co-60 is selected by default. A different nuclide can be selected from the element and mass drop-down menus. The default source strength is 1 gram. In the Unit/Quantity table, this source strength is shown in Becquerel (Bq), Curie (Ci), Number of Atoms. Hence 1 g Co-60 corresponds to a source strength of 4.187E13 Bq, 1.132E3 Ci or 1.005E22 atoms.

Element: Mass:

Co 60

Nuclide Chart Button:



shows the location of the selected nuclide on the nuclide chart.

Unit/Quantity Selector

[\[edit\]](#)

The input unit can be changed in the Unit drop down menu. The default value is 1 gram. Had the value 1 Curie been selected, on pressing the Update button, the corresponding values in grams, Bq, number of atoms are shown in the Unit/Quantity table.

Unit

Quantity

Curies

Grams

Becquerel

Curies

Number Of Atoms

1.0000E+00

Unit/Quantity Table

Once the unit and quantity have been selected in the Unit/Quantity Selector, the source strength in other units is given in the Unit/Quantity table, by pressing the update button. In the table below, results are shown for 1 Ci Co-60.

Unit	Quantity
Grams	8.8366E-04
Becquerel	3.7000E+10
Curies	1.0000E+00
Number of Atoms	8.8790E+18

Exercises! Mass-Activity Calculator

1. Calculate the specific activities of C-14 and S35? ($1.7\text{E}11$ Bq/g (4.5 Ci/g), $1.6\text{E}15$ Bq/g ($4.3\text{E}4$ Ci/g)). After what time is the activity reduced by 50% ?(5700 y, 87.32 d)
2. The activity of Sr-90 is 18,000 transformations per minute. What is the mass of Sr-90? (Ans. mass = $5.88\text{E}-11\text{g}$). After what time is the activity reduce to 25% of its initial value? (57.6 y)
3. 6 g of carbon from a piece of wood found in an ancient temple is analyzed and found to have an activity of 10 transformations per minute per gram (from C-14). How many atoms of C-14 are present in the sample and what is their mass? ($2.6\text{E}11$ atoms, mass = $6.0\text{E}-12$ g)
4. The environmental burden of C-14 is as follows: In the atmosphere 4 MCi, in plants 13 MCi, in the oceans 240 MCi. What are the masses of C-14 in a) the atmosphere b) in plants and c) in the oceans? (893 kg, 2.9 metric tons, 53.6 tonnes)
5. The concentration of potassium (K) in humans is about 1.7 g/kg. How much potassium does an average person (weight 80 kg) contain? (136 g). What is the abundance of K-40 in natural potassium?. What is the mass and activity of K-40 in this person? (0.0117% , $1.59\text{E}-2$ g, 4.2 kBq).
6. Calculate the specific activities of H-3, Sr-90, U-238? ($3.6\text{E}14$ Bq/g, $5.1\text{E}12$ Bq/g, $1.2\text{E}4$ Bq/g)
7. What is the maximum alpha particle emission rate from 1 μg Ra-226? ($3.7\text{E}4$ alphas/s)
8. Three hundred MBq (5.4mCi) of Po-210 are required for an ionisation source. What is the mass of Po-210? (1.8 μg)
9. How many grams of Y-90 are in secular equilibrium with 1 mg Sr-90? (0.25 μg)

For further information see our natural radioactivity applet at:

<http://www.nucleonica.net/naturalra.aspx>

nucleonica



Thanks!



nucleonica

